


10. Stalker integration


There are two ways to integrate MAG STB with Ezserver, they are to use Stalker with original MAG UI

You need to add a user with password in Ezserver Panel first:

- Add a user by MAC Address and Serial Number in Ezserver User Panel. Take care the case sensitivity of MAC ID from MAG box with User Name of Ezserver Panel.



- If you see the below screen, it means the Username of Ezserver Panel and MAC ID from Mag box are not same for the case sensitivity.



Ex. The MAC ID of MAG stb is 00:1A:70:1C:FF:BB, the username is defined by 00:1a:70:1c:ff:bb, so change username to 00:1A:70:1C:FF:BB.

- Source URL without protection
- Create a user in EZserver Panel (ex. username: test, password: 1234)
 - Login stalker portal

- Click “Sections: IPTV channels”
- add ezserver links as below into IPTV Channels
 - `http://ezserver_ip:port/ChannelName?u=username;p=password`
 - ex. `http://192.168.0.8:8000/TV1?u=test;p=1234`
- B. Source URL with protection
- Login stalker portal
- Click “Sections: IPTV channels”
- add ezserver links as below into IPTV Channels
 - `http://ezserver_ip:port/ChannelName`
 - ex. `http://192.168.0.8:8000/TV1`
 - **Do not need to add username and password in the link, just add Channel Name.**
- add the extra code in `stalker_portal-x.x.x/c/player.js`
 - stalker newest version
 - ◆ line 2525: `this.play_now(cmd);`
 - ◆ Add `cmd += '?u='+stb.profile.mac+';p='+stb.serial_number;` before line 2525

■ Ex :

Line 2525: `cmd += '?u='+stb.profile.mac+';p='+stb.serial_number;`

Line 2526: `this.play_now(cmd);`

```

2523
2524
2525 cmd += '?u='+stb.profile.mac+';p='+stb.serial_number;
2526 this.play_now(cmd);
2527

```

- stalker newest version with MPEG TS output
 - ◆ line 2525: `this.play_now(cmd);`
 - ◆ Add `cmd += '?u='+stb.profile.mac+';p='+stb.serial_number+';muxer=ts';` before line 2525

■ Ex :

Line 2525: `cmd += '?u='+stb.profile.mac+';p='+stb.serial_number+';muxer=ts';`

Line 2526: `this.play_now(cmd);`

```

2523
2524
2525 cmd += '?u='+stb.profile.mac+';p='+stb.serial_number+';muxer=ts';
2526 this.play_now(cmd);
2527

```

- stalker V4 version
 - ◆ **line 2435 : `this.create_link('remote_pvr', cmd, 0);`**
 - ◆ **Add `cmd.cmd += '?u='+stb.mac+';p='+stb.serial_number;` before line 2435**
- Ex :
 - ◆ **Line 2435: `cmd.cmd += '?u='+stb.mac+';p='+stb.serial_number;`**
 - ◆ **Line 2436: `this.create_link('remote_pvr', cmd, 0);`**
- stalker V5 version
 - ◆ **line 2438: `this.play_now(cmd);`**
 - ◆ **Add `cmd += '?u='+stb.mac+';p='+stb.serial_number;` before line 2438**
- Ex :
 - ◆ **Line 2438: `cmd += '?u='+stb.mac+';p='+stb.serial_number;`**
 - ◆ **Line 2439: `this.play_now(cmd);`**