Ezhometech   www.ezhometech.com

Ezserver Qucik Guide

Signage Version

www.ezhometech.com

Updated :07/29/2017

Version : 1.0.001

Ezhometech

Content

Ezhometech

1. Installation

ezserver_signage.zip contains a folder "**ezserver_signage**" that includes ezserver image, system configuration.

- o unzip **ezserver_signage.zip**
- o enter **ezserver_signage** folder
- o double click **Ezserver12.exe**
- o send **serial_number.txt to <u>sales@ezhometech.com</u> for license activation.**
- o click **Action: Open Panel** to open Ezserver Digital Signage panel in a browser.

There are two ways to shutdown ezserver

- Select Action:Shutdown
- Login Ezserver System Management

Ezhometech

2. Digital Signage Panel

Digital Signage Panel is based on Ezserver API to provide managements for administrators, It supports Internet browser such as *Internet Explore*, *Chrome*, *Firefox* or *Safari* to login by the below URL path

http://Server_IP:18000/admin/index.htm

Ezserver

- HOME
- USER
- **GROUP**
- **LAYOUT**
- **PLAYER**
- CHANNEL
- MOVIE
- ALERT
- BLACKLIST
- SETTING
- STATISTICS
- LOG
- SHUTDOWN

System Information

* ezhometech EZserver
* Version: **Signage 2.0(07/29/17)**
* Serial Number: 0ACA80D3AEDF9A53B5C846C5C61F5

* Start at: **2017/1/13 18:55:35**
* Uptime: **0 Days 0:01:12**

* Groups: **2**
* Subscribers: **19**
* Streaming Connections: **1**
* Blacklist IP: **0**

* Channels: **30**
* Active Channels: **30**
* Movies: **30**

* Upload Bandwidth: **1.57** Mbps
* Download Bandwidth: **0.83** Mbps

Digital Signage Panel provides the below management

- **Home:** System Information.
- **User:** Subscriber Management
- **Group:** Group Management
- **Layout:** Screnn Layout Generation.
- **Player:** Online Player Information
- **Channel:** Channel Management
- **Movie:** Movie Management
- **Alert Player:** Alert Player Information
- **Blacklist:** Automatic blacklist management
- **Setting:** Protocol port setting
- **Statistics:** Channel Statistics

Ezhometech

- **Shutdown:** Shutdown Ezserver

- **Log:** System Log

3. Add New Layout

Follow the below steps to add new layout.

Step1: Click "Layout" Button.

Step2: Click "<" or ">" Button to select one of screen layout.

Step3: Select resolution and video width and height.

Step4: press "Create layout" button

Step5: Add new video, image in Displayed windows.

4. Administrator password change

Use Internet browser such as *Internet Explore*, *Chrome*, *Firefox* or *Safari* to enter System Management by the URL path : **http://Server_IP:18000/admin/index.htm**

Login Panel by user id "**root**" and password, then click **User button** to change root password.

## 5. Digital Signage Player Requirement

Software Requirement

Items	Version
EZserver Digital Signage Panel	Release 2.0
Google Android	Above 4.x, 5.x, 6.x

Hardware Requirement

Items	Specification
Processor	Above 1.0GHz
Memory	At least 1GB for 200 channels
Network Interface	802.11 a/b/g/n
Disk Space	248K bytes

6. Digital Signage Player Setting

When you start Digital Signage Player first time, you have to input EZserver Information into the Setting. The Setting includes User Name, Password, EZserver Domain Name / IP and Port No. as below: